

Scapy BTBB Demo

- This demo serves as a brief scapy tutorial but more importantly, it illustrates the btbb layer in Scapy
- it also demonstrates utilities and helpers provided by the library
- if you have issues installing the btbb scapy module, please refer to the documentation at hackgnar.com

library imports

- import everything from scapy for the demo
- import everything from the btbb Scapy module

```
In [1]: from scapy.all import *  
        from btbb import *
```

```
WARNING: No route found for IPv6 destination :: (no default route?)  
WARNING:scapy.runtime:No route found for IPv6 destination :: (no default  
route?)
```

Open btbb pcap file:

- btbb pcap files for this demo were created with Kismet and Ubertooth
 - these can also be created by other means such as USRP and Kismet, etc

```
In [2]: btbb_pcaps = PcapReader('../data/small.pcapbtbb')
```

Read one packet from the pcap file:

- btbb packet is read pcap file and instantiated as Scapy packet

```
In [3]: pkt = btbb_pcaps.read_packet()
```

Packet sample:

- nothing special about this packet. Looks like a typical Ethernet packet
- btbb packets are layered on top of the ethernet layer much like the wireshark btbb layout
- when nothing is present in the btbb layer, these look exactly like ethernet packets

```
In [4]: pkt.show()
```

```
###[ Ethernet ]###
dst      = 00:00:00:00:00:00
src      = 00:00:00:ed:1d:9c
type     = 0xffff0
```

Interactively iterate through packets:

- we can run the following over and over to look through packets

```
In [5]: pkt = btbb_pcaps.read_packet()
        pkt.show()
```

...

```
In [6]: pkt.summary()
```

```
Out[6]: '00:00:00:ed:1d:9c > 00:00:00:00:00:00 (0xffff0)'
```

Conditionally iterate through btbb pcap file:

- iterate through the pcap file
- display summary data for all packets
- display detailed data if a btbb payload exists

```
In [7]: for pkt in btbb_pcaps:
        print pkt.summary()
        if pkt.haslayer('BtbbPayload'):
            pkt.show()
            break
```

```
00:00:00:ed:1d:9c > 00:00:00:00:00:00 (0xffff0)
00:00:00:ed:1d:9c > 00:00:00:00:00:00 (0xffff0)
00:00:00:ed:1d:9c > 00:00:00:00:00:00 (0xffff0)
00:00:00:ed:1d:9c > 00:00:00:00:00:00 (0xffff0)
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket / BtbbPayload
###[ Ethernet ]###
dst      = 00:00:00:00:00:00
src      = 00:00:36:ed:1d:9c
type     = 0xffff0
###[ btbb ]###
###[ meta ]###
        CLK      = 0x7000000L
        Channel  = 39L
```

```

        Padding      = 0L
        known address bits= 32 (NAP unknown)
        known clock bits= 6
####[ packet ]###
        type         = DH1/2-DH1
        LT_ADDR      = 0x1L
        SEQN_Flag    = 1L
        ARQN_Flag    = 0L
        FLOW_Flag    = 1L
        HEC          = 0xc9
####[ payload ]###
        header_length= 3L
        header_flow= 1L
        header_LLID= 0L
        body         = '\x0e\x13\xd1'
        CRC          = 0x6209L

```

Packet list

- instantiate the rest of the packets into a list of packets

```
In [8]: btbb_pkt_list = btbb_pcaps.read_all()
```

```
In [9]: btbb_pkt_list
```

```
Out[9]: <small.pcapbtbb: TCP:0 UDP:0 ICMP:0 Other:456>
```

```
In [10]: print len(btbb_pkt_list)
         for item in btbb_pkt_list[:5]:
             print item.summary()
```

```

456
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket

```

Write btbb pcap files:

- we can also write btbb packets back to new pcap files if we like

```
In [11]: pcapbtbb_writer = PcapWriter('../data/new_pcap_file.pcapbtbb')
pcapbtbb_writer.write(btbb_pkt_list)
```

```
In [12]: !ls -li new_pcap_file.pcapbtbb
```

```
ls: new_pcap_file.pcapbtbb: No such file or directory
```

```
In [13]: new_btbb_pkts = PcapReader("../data/new_pcap_file.pcapbtbb")
pkts = new_btbb_pkts.read_all()
print len(pkts)
for i in pkts[:5]:
    print i.summary()
```

```
412
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
```

```
In [14]: new_btbb_pkts.close()
btbb_pcaps.close()
```

Btbb Pcap File Stream:

- Generic way to stream data from bluetooth baseband hardware
- Relies on the fact that they have a way to write btbb pcap files
- Allows for interactive real time packet monitoring

```
In [15]: #log_dir = "../data/new_pcap_file.pcapbtbb"
#latest_file = !ls -tl $log_dir/head -1
#latest_file = log_dir + '/' + latest_file[0]
latest_file = "../data/new_pcap_file.pcapbtbb"
```

```
In [16]: btbb_stream = BtbbPcapStreamer(latest_file)
```

```
In [17]: for pkt in btbb_stream.stream(output='packet', stop=True):
    print pkt.summary()
```

```
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
```

```

BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket

```

```
In [18]: btbb_stream.close()
```

Btbb layer helper methods

- a sample of some of the helper methods provided by scapy btbb
- lets open a new pcap file, read in the packets and define some vars first

```
In [19]: manuf_file='../data/wireshark_manuf'
!wc -l $manuf_file

22118 ../data/wireshark_manuf
```

```
In [20]: btbb_pcaps = PcapReader('../data/small.pcapbtbb')
pkts = btbb_pcaps.read_all()
```

```
In [21]: for i in range(10):
          print i , pkts[i].summary()

0 00:00:00:ed:1d:9c > 00:00:00:00:00:00 (0xffff0)
1 00:00:00:ed:1d:9c > 00:00:00:00:00:00 (0xffff0)
2 00:00:00:ed:1d:9c > 00:00:00:00:00:00 (0xffff0)
3 00:00:00:ed:1d:9c > 00:00:00:00:00:00 (0xffff0)
4 00:00:00:ed:1d:9c > 00:00:00:00:00:00 (0xffff0)
5 00:00:00:ed:1d:9c > 00:00:00:00:00:00 (0xffff0)
6 00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket / BtbbPayload
7 00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
8 00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket
9 00:00:36:ed:1d:9c > 00:00:00:00:00:00 (0xffff0) / Btbb / BtbbMeta /
BtbbPacket

```

Vendor lookup:

- can lookup vendor based on a bluetooth address
- can lookup vendor based on packet
- vendor determination is more accurate when both nap and uap are known
- when only a uap is know, a list of possible vendors and associated nap is returned
- if your wireshark manuf file is not in a default location you must specify as seen below

```
In [22]: get_vendor('00:11:36:ed:1d:9c', manuf_file=manuf_file)
```

```
Out[22]: [('00:11:36', 'Goodrich')]
```

```
In [23]: possible_vendors = get_vendor(pkts[6],manuf_file=manuf_file)
```

```
In [24]: len(possible_vendors)
```

```
Out[24]: 61
```

```
In [25]: possible_vendors
```

```
Out[25]: [('00:00:36', 'Atari'),  
          ('00:01:36', 'Cybertan'),  
          ('00:02:36', 'Init'),  
          ('00:03:36', 'ZetesTec'),  
          ('00:04:36', 'ElansatT'),  
          ('00:05:36', 'DanamCom'),  
          ('00:06:36', 'JedaiBro'),  
          ('00:07:36', 'DataVide'),  
          ('00:09:36', 'Ipetroni'),  
          ('00:0A:36', 'SynelecT'),  
          ('00:0B:36', 'Producti'),  
          ('00:0C:36', 'SharpTak'),  
          ('00:0D:36', 'WuHanRou'),  
          ('00:0E:36', 'Heinesys'),  
          ('00:0F:36', 'Accurate'),  
          ('00:10:36', 'Inter'),  
          ('00:11:36', 'Goodrich'),  
          ('00:12:36', 'Consentr'),  
          ('00:13:36', 'Tianjin7'),  
          ('00:14:36', 'QwertyEl'),  
          ('00:15:36', 'Powertec'),  
          ('00:16:36', 'QuantaCo'),  
          ('00:17:36', 'Iitron'),  
          ('00:18:36', 'Reliance'),  
          ('00:19:36', 'Sterlite'),  
          ('00:1A:36', 'Aipermon'),  
          ('00:1B:36', 'TsubataE'),  
          ('00:1C:36', 'InewitNv'),  
          ('00:1D:36', 'Electron'),
```

```
( '00:1E:36', 'Ipte'),
( '00:1F:36', 'BellwinI'),
( '00:20:36', 'BmcSoftw'),
( '00:21:36', 'Motorola'),
( '00:22:36', 'VectorSp'),
( '00:23:36', 'MetelSRO'),
( '00:24:36', 'Apple'),
( '00:25:36', 'OkiElect'),
( '00:26:36', 'Motorola'),
( '00:30:36', 'RmpElekt'),
( '00:40:36', 'TribeCom'),
( '00:50:36', 'Netcam'),
( '00:60:36', 'AitAustr'),
( '00:80:36', 'ReflexMa'),
( '00:90:36', 'Ens'),
( '00:A0:36', 'AppliedN'),
( '00:C0:36', 'RaytechE'),
( '00:D0:36', 'Technolo'),
( '00:E0:36', 'Pioneer'),
( '08:00:36', 'Intergra'),
( '0C:E9:36', 'ElimosSr'),
( '58:E6:36', 'EvrSAFE'),
( '64:0E:36', 'Taztag'),
( '68:5B:36', 'Powertec'),
( '6C:83:36', 'SamsungE'),
( '88:10:36', 'PanodicS'),
( '8C:92:36', 'AusLinxT'),
( '9C:4E:36', 'IntelCor'),
( 'AC:72:36', 'LexkingT'),
( 'B0:AA:36', 'Guangdon'),
( 'E0:26:36', 'NortelNe'),
( 'EC:F2:36', 'Neomonta')]
```

Distinct bluetooth address lookup:

- distinct bluetooth addresses can be looked up
- useful for quickly determining what devices are in a list of packets
- useful for passing to other tools/modules for analysis, exploitation, etc

```
In [26]: bt_addrs = get_btaddress(*pkts)
         bt_addrs
```

```
Out[26]: ['00:00:00:c3:ec:46',
          '00:00:00:db:c1:fa',
          '00:00:36:ed:1d:9c',
          '00:00:d2:59:84:d9',
          '00:00:00:ff:c4:ab']
```

```
In [27]: import bluetooth
         for addr in bt_addrs:
```

```
print bluetooth.lookup_name(addr)
```

--

ImportError Traceback (most recent call
last)

<ipython-input-27-8b458bdeb67c> in <module>()

```
----> 1 import bluetooth
      2 for addr in bt_addrs:
      3     print bluetooth.lookup_name(addr)
```

ImportError: No module named bluetooth